

Release Notes EGK EGU EZU

Siemens FB IO-Link Acyclic

Version	Comment	Supported Device	Interface
1.0.4 Compatibility: Siemens TIA 17 S7 1500 und S7 1200	Changelog: Input variable "i_Port" implemented to directly specify the port of the master. This made it compatible with Siemens IO-Link masters of the ET200ECO, the ET200SP, the CM module of the 1500 series and the SM module of the 1200 series Text Fixes Required Options: none Known issues: none	EZU: all types with firmware version 5.3 EGU: all types with firmware version 5.1 - 5.3 EGK: all types with firmware version 5.1 - 5.3	IO-Link 1.0 and 1.1
1.0.3 Compatibility: Siemens TIA 17 S7 1500 und S7 1200	Changelog: removed the Master selection. The CAP number must now be entered directly as some master manufacturers have new numbers. Required Options: none Known issues: none	EGU EGK EZU	IO-Link 1.0 and 1.1
1.0.2 Compatibility: Siemens TIA 17 S7 1500 und S7 1200	Changelog: Changed IOLink_Device Funktion Block from V4.0 to V5.0 Required Options: none Known issues:	EGU EGK EZU	IO-Link 1.0 and 1.1

	none		
1.0.1 Compatibility: Siemens TIA 17	Changelog: Bug fixing at Read Prozess Required Options: none Known issues: none	EGU EGK EZU	IO-Link 1.0 and 1.1
1.0.0 Compatibility: Siemens TIA 17	Changelog: Release Funktion Block Required Options: none Known issues: none	EGU EGK EZU	IO-Link 1.0 and 1.1