

Release Notes EGK EGU EZU

Siemens FB IO-Link Cyclic

Version	Comment	Supported Device	Interface
1.0.5 Compatibility: Siemens TIA 17 S7 1500 und S7 1200	Changelog: - i_OFFSET_INPUT_ADRESSE implemented - i_OFFSET_OUTPUT_ADRESSE implemented - Changed #GETIO_Instance to #GETIO_PART_Instance - Changed #SETIO_Instance to #SETIO_PART_Instance - REGION "Release FB" moved to the end of the Funktion Block - Changed the Output Pins Warning and Error from Word to Byte - Plugged in the Auditional Warning Code as Byte. Required Options: Known issues:	EZU: all types with firmware version 5.3 EGU: all types with firmware version 5.1 - 5.3 EGK: all types with firmware version 5.1 - 5.3	IO-Link 1.0 and 1.1
1.0.1 Compatibility: Siemens TIA 17 S7 1500 und S7 1200	Changelog: - New Bit "Brake Test" - Changed Bit Names not the Funktions behind Required Options: Known issues:	EGU EGK EZU	IO-Link 1.0 and 1.1
1.0.0 Compatibility: Siemens TIA 17 S7 1500 und S7 1200	Changelog: Initial Version Required Options: Known issues:	EGU EGK EZU	IO-Link 1.0 and 1.1

--	--	--	--