

Release Notes EGU EGK EZU

Allen Bradley FB EthernetIP Cyclic

Version	Comment	Supported Device	Interface
1.0.3 Compatibility: Studio 5000 V35.00.00	Changelog: - Compatible with FW 5.3 Protokol - order when deleting bits changed Required Options: none Known issues: none	EZU: all types with firmware version 5.3 EGU: all types with firmware version 5.1 - 5.3 EGK: all types with firmware version 5.1 - 5.3	EthernetIP
1.0.2 Compatibility: Studio 5000 V35.00.00	Changelog: - Compatible with FW 5.2 Protocol - Compatible with FW 5.3 Protocol - New Bit "Brake Test" - Changed Bit Names not the Functions behind Required Options: none Known issues: none	EZU: all types with firmware version 5.3 EGU: all types with firmware version 5.1 - 5.3 EGK: all types with firmware version 5.1 - 5.3	EthernetIP
1.0.1 Compatibility:	Changelog: Bugfix - di_out_OUTPUT_DATA_Gripper_DW_2 := di_in_VELOCITY;	EGU EGK EZU	EthernetIP

Studio 5000 V35.00.00	- di_out_OUTPUT_DATA_Gripper_DW_3 := di_in_GRIPPING_FORCE; Required Options: none Known issues: none		
1.0.0 Compatibility: Studio 5000 V35.00.00	Changelog: Initial Version Release Funktion Block TagType="Base" DataType="BOOL" Usage="Input" Radix="Binary" Required="false" Visible="true" ExternalAccess="Read Only" Required Options: none Known issues: none	EGU EGK EZU	EthernetIP